



Virtual Phone User's Guide

Palm OS® 5 SDK (68K) R3

CONTRIBUTORS

Written by Brian Maas and Michael Spratt

Production by: <dot>PS Document Production Services

Engineering contributions by Yann Cheri, Sylvain Balerin, and Eric Fabre.

Copyright © 1996 - 2003, PalmSource, Inc. and its affiliates. All rights reserved. This documentation may be printed and copied solely for use in developing products for Palm OS® software. In addition, two (2) copies of this documentation may be made for archival and backup purposes. Except for the foregoing, no part of this documentation may be reproduced or transmitted in any form or by any means or used to make any derivative work (such as translation, transformation or adaptation) without express written consent from PalmSource, Inc.

PalmSource, Inc. reserves the right to revise this documentation and to make changes in content from time to time without obligation on the part of PalmSource, Inc. to provide notification of such revision or changes.

PALMSOURCE, INC. AND ITS SUPPLIERS MAKE NO REPRESENTATIONS OR WARRANTIES THAT THE DOCUMENTATION IS FREE OF ERRORS OR THAT THE DOCUMENTATION IS SUITABLE FOR YOUR USE. THE DOCUMENTATION IS PROVIDED ON AN "AS IS" BASIS. PALMSOURCE, INC. AND ITS SUPPLIERS MAKE NO WARRANTIES, TERMS OR CONDITIONS, EXPRESS OR IMPLIED, EITHER IN FACT OR BY OPERATION OF LAW, STATUTORY OR OTHERWISE, INCLUDING WARRANTIES, TERMS, OR CONDITIONS OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND SATISFACTORY QUALITY. TO THE FULL EXTENT ALLOWED BY LAW, PALMSOURCE, INC. ALSO EXCLUDES FOR ITSELF AND ITS SUPPLIERS ANY LIABILITY, WHETHER BASED IN CONTRACT OR TORT (INCLUDING NEGLIGENCE), FOR DIRECT, INCIDENTAL, CONSEQUENTIAL, INDIRECT, SPECIAL, OR PUNITIVE DAMAGES OF ANY KIND, OR FOR LOSS OF REVENUE OR PROFITS, LOSS OF BUSINESS, LOSS OF INFORMATION OR DATA, OR OTHER FINANCIAL LOSS ARISING OUT OF OR IN CONNECTION WITH THIS DOCUMENTATION, EVEN IF PALMSOURCE, INC. OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

PalmSource, the PalmSource logo, AnyDay, EventClub, Graffiti, HandFAX, HandMAIL, HandSTAMP, HandWEB, HotSync, the HotSync logo, iMessenger, MultiMail, MyPalm, Palm, the Palm logo, the Palm trade dress, Palm Computing, Palm OS, Palm Powered, PalmConnect, PalmGear, PalmGlove, PalmModem, PalmPak, PalmPix, PalmPoint, PalmPower, PalmPrint, Palm.Net, Simply Palm, ThinAir, and WeSync are trademarks of PalmSource, Inc. or its affiliates. All other product and brand names may be trademarks or registered trademarks of their respective owners.

IF THIS DOCUMENTATION IS PROVIDED ON A COMPACT DISC, THE OTHER SOFTWARE AND DOCUMENTATION ON THE COMPACT DISC ARE SUBJECT TO THE LICENSE AGREEMENT ACCOMPANYING THE COMPACT DISC.

Virtual Phone User's Guide
Document Number 4004-003
July 30, 2003
For the latest version of this document, visit
<http://www.palmos.com/dev/support/docs/>.

PalmSource, Inc.
1240 Crossman Avenue
Sunnyvale, CA 94089
USA
www.palmsource.com

Table of Contents

About This Document	vii
What This Document Contains	vii
Related Information.	viii
Additional Resources	viii
 1 Introducing Virtual Phone	 1
What Virtual Phone Can Do for You.	1
About Virtual Phone	1
What Virtual Phone Does	2
What Virtual Phone Does Not Do.	2
Virtual Phone Background Information	2
Virtual Phone Overview	3
Configuration Files	3
SMS Message Files	4
AT Command Log Files	4
Phone Book Files	4
Configuration Files Summary	5
 2 Getting Started	 7
Configuring Palm OS Emulator.	7
Properties	8
Redirection Settings	9
Configuring the Phone Preferences	10
Phone Settings in the Prefs Application	10
 3 Using Virtual Phone	 13
Virtual Phone Window	13
File Menu	14
Edit Menu.	14
View Menu	14
Tools Menu	15
Service Configuration Dialog Box.	17
General Tab	18
Phone Settings.	18

Power	20
Sound	20
Network Tab.	21
Networks	22
Network Parameters	24
Phone Books Tab	27
Phone Books	28
Security Tab	29
SIM	30
SMS Tab	33
SIM Tab.	35
Speech Tab	36
GPRS Tab	40
Response Preferences Dialog Box	43
Connection Setup Dialog Box	51
Fixing Connection Problems	52
Speech Calls Dialog Box	53
Short Message Dialog Box	55
Encode/Decode an SMS Tab.	56
SMS Center	56
SMS Storage Tab	56
Messages	57
Sent SMS History Tab.	58
Messages	59

A Log and Database Files 61

Configuration Files	62
Application Configuration File - VAppCfg.db.	62
VAppCfg.db	62
Available Network File - AvailableNwk.db	65
AvailableNwk.db	65
Phone Book Databases	65
Phone Book Database Organization	66
SMS Files	66
SmsStore.db File	68

SmsStoreSend.db File.	68
Log File	69
VPAppATLog.log	69

About This Document

Virtual Phone is a development tool that can help you test Palm OS applications that communicate with a mobile telephone. Virtual Phone is a part of Palm OS 5 SDK (68K).

Virtual Phone User's Guide will help you understand how to use Virtual Phone with Palm OS Emulator to test your telephony applications. This introduction discusses what materials are included in this document and what conventions are used.

What This Document Contains

- [Chapter 1, “Introducing Virtual Phone,”](#) on page 1
This chapter introduces you to Virtual Phone concepts and provides you with an overview of Virtual Phone.
- [Chapter 2, “Getting Started,”](#) on page 7
This chapter helps you setup Virtual Phone and configure it to work with Palm OS Emulator.
- [Chapter 3, “Using Virtual Phone,”](#) on page 13
This chapter describes how to use Virtual Phone to test Palm™ applications which are written to communicate with mobile telephones.
- [Appendix A, “Log and Database Files,”](#) on page 61
This appendix describes the log files and databases that are used with Virtual Phone.

Related Information

- *Palm OS Programmer's API Reference*

Wherever appropriate, *Virtual Phone User's Guide* makes reference to functions and constants described in *Palm OS Programmer's API Reference*. You can use this information to relate the Telephony Manager services to the Virtual Phone services.

- *Palm OS Programmer's Companion*, vol. II, *Communications*

You should be familiar with the Telephony Manager concepts described in *Palm OS Programmer's Companion*, vol. II, *Communications*.

- *Using Palm OS Emulator*

You can learn about Palm OS Emulator in this manual.

Additional Resources

- Documentation

Palm publishes its latest versions of this and other documents for Palm OS developers on the Palm OS web site:

<http://www.palmos.com/dev/support/docs/>

- Training

Palm and its partners host training classes for Palm OS developers. Check the Palm OS web site for topics and schedules:

<http://www.palmos.com/dev/training/>

- Knowledge Base

The Knowledge Base is a fast web-based database of technical information. Search for frequently asked questions (FAQs), sample code, white papers, and the development documentation:

<http://www.palmos.com/dev/tech/kb/>

Introducing Virtual Phone

Virtual Phone is a tool which simulates a mobile phone. Virtual Phone can help you develop and test applications which use the Telephony Manager API. Virtual Phone recognizes Telephony Manager AT commands and responds exactly the same as a mobile phone. Virtual Phone is also capable of simulating events like incoming voice calls and SMS messages.

What Virtual Phone Can Do for You

- Virtual Phone provides developers with a fast and simple tool for implementing, debugging, and testing a telephony application during the initial development stages.
- Virtual Phone reduces debugging and testing time for telephony applications which can be a lengthy process when using a real cellular phone.
- Virtual Phone eliminates delays due to slow phone device answer time and delays in wireless connections.
- Virtual Phone eliminates costs associated with establishing a real connection in order to test an outgoing SMS message. These costs are prohibitive.
- Virtual Phone provides an intermediate solution before final testing with a real phone.

About Virtual Phone

Virtual Phone is not intended to test the different phone drivers that can be used to communicate with telephones. It is designed to test applications which communicate with a mobile telephone. Virtual Phone is based upon the functioning of a standard GSM default

phone driver. This implies that any functions not supported by a standard GSM phone driver are not supported by Virtual Phone.

What Virtual Phone Does

Virtual Phone supports all the services offered by the Telephony Manager.

Virtual Phone considers the state of the telephone when performing some operations. For example, it accepts emergency calls when a PIN code is expected. Otherwise, no operations can be performed on Virtual Phone if the Security State is not set to Ready.

What Virtual Phone Does Not Do

Virtual Phone does not simulate automatic changes in the state of the telephone such as fluctuations in the network level or progressive drain of the battery. These state parameters can be manually changed in the configuration panel.

Virtual Phone Background Information

Virtual Phone simulates a standard mobile telephone working under a Global System for Mobile Communications (GSM) Network.

When working with Virtual Phone, you should understand the following background information:

- Telecommunication standards

The European Telecommunication Standards Institute (ETSI) has established the European Telecommunication Standards (ETS) which contains a series of attention (AT) commands recognized by a mobile phone. It is assumed that you are aware of these standards. For information on these standards, see *GSM Technical Specification 07.07 Reference TS/SMG-040707Q* and *GSM Technical Specification 07.05: SMS AT Commands*.

- Telephony Manager

The Palm OS® provides the Telephony Manager, which programmers can use to write applications that interact with telephony services. For information about the Telephony Manager, see the Telephony Manager chapter in *Palm OS Programmer's Companion*, vol. II, *Communications*.

- Palm OS Emulator

Palm OS Emulator is a hardware emulator for the Palm OS platform. You can use Palm OS Emulator to test your applications. For information on Palm OS Emulator, see *Using Palm OS Emulator*.

Virtual Phone communicates with Palm OS Emulator and processes AT commands issued by applications running under the Palm OS. Processing includes analyzing AT commands sent from the Palm OS Emulator to the Virtual Phone, forwarding commands to the appropriate Service (Network, Security, etc.) and generating both AT command replies and unsolicited events (for example, RING . . .). Virtual Phone logs and saves exchanged AT commands and configuration data.

Virtual Phone Overview

Virtual Phone requires several ASCII format text files, which use the standard INI file format. Virtual Phone will create these files if they do not already exist.

There are two configuration files, two SMS message files and one AT command log file. Virtual Phone also uses the eleven ETSI standard phone book files.

Configuration Files

The configuration files, `VPAppCfg.db` and `AvailableNwk.db`, store configuration and network data:

- The configuration file `VPAppCfg.db` stores configuration data relevant to Virtual Phone's Configuration, Information, Speech Call, Network, Phone Book, Security, Communication and Short Message Services (SMS) settings.

- The configuration file `AvailableNwk.db` stores the list of networks, their IDs, and names.

SMS Message Files

Two SMS files, `SmsStore.db` and `SmsSentStore.db`, store SMS messages which are normally not saved on a mobile telephone.

AT Command Log Files

AT commands are stored in the `VPAppATLog.log` file. This log file is created to save all the AT commands exchanged between Virtual Phone and Palm OS Emulator. To save the contents of the log file, you should rename it after quitting Virtual Phone. The next time you use Virtual Phone, it will overwrite the `VPAppATLog.log` file. This file is locked and inaccessible during Virtual Phone execution.

The file `VPMainLog.txt` is used for logging the results of the AT commands. Note that this file is updated only when `View > Disable Log` is unchecked and when the Virtual Phone main log window is full.

Phone Book Files

Virtual Phone supports the ETSI standard phone book files:

- `PhbDC.db` - Mobile Equipment (ME) dialed calls list
- `PhbEN.db` - SIM or ME emergency number
- `PhbFD.db` - Fixed phone book
- `PhbLD.db` - Last dialed list
- `PhbMC.db` - ME missed calls list (received calls that were unanswered)
- `PhbME.db` - Phone phone book
- `PhbMT.db` - Combined ME and SIM phone book
- `PhbON.db` - SIM or ME own numbers (MSISDNs) list
- `PhbRC.db` - ME received calls list
- `PhbSM.db` - SIM phone book
- `PhbTA.db` - Terminal Adapter (TA) phone book

The phone book files all have the same format, which consists of an index number, name, and phone number.

Configuration Files Summary

All configuration files, phone book files, and log files are created in the directory where Virtual Phone is executed. As a result, only one version of Virtual Phone can be executed from the same directory.

You will need to use an editor (for example, Notepad) when you edit the files `AvailableNwk.db` and the eleven phone book files.

We strongly recommend that you keep a back-up copy of these files for security and recovery reasons.

We do not recommend editing the `VPAppCfg.db` file directly, but you may access configuration variables without using Virtual Phone's developer interface. For data elements displayed on Virtual Phone's screens, this book describes the corresponding elements in the appropriate database file. This information is provided in order to help you control Virtual Phone's behavior, which is directly controlled by these files.

WARNING! Virtual Phone creates databases in the directory that it is running and writes and reads from them constantly. For this reason, you cannot simultaneously run two instances of Virtual Phone from the same directory. This will cause conflicts during file access.

Introducing Virtual Phone

Virtual Phone Overview

Getting Started


To use Virtual Phone, you need to configure Palm OS Emulator to work with Virtual Phone.

- “[Configuring Palm OS Emulator](#)” on page 7
- “[Configuring the Phone Preferences](#)” on page 10

Configuring Palm OS Emulator

In order to configure Palm OS Emulator, right-click the Palm OS Emulator window, and select **Settings > Properties**, as shown [Figure 2.1](#).


Figure 2.1 Configuring Palm OS Emulator



Properties

Use the Properties dialog, [Figure 2.2](#), to configure Palm OS Emulator's communication parameters. These parameters must correspond to Virtual Phone's parameters in order to establish communication between the two applications (see "[Tools Menu](#)" on page 15 and "[Connection Setup Dialog Box](#)" on page 51 for more information).

Figure 2.2 Palm OS Emulator Properties Dialog Box



Redirection Settings

The **Serial Port** selection item provides the following options:

- **No Port**
- **COM1**
- **COM2**
- **TCP/IP**

If you select **COM1** or **COM2**, you will need to connect a null modem cable between the two serial ports of your computer. You must configure Virtual Phone to open the port not being used by the Palm OS Emulator.

If you select **No Port**, you will get an error if an application tries to access Serial Manager I/O functions.

Virtual Phone works best if you select **TCP/IP**. Selecting **TCP/IP** redirects all data transfers intended for the serial port to a **TCP/IP** socket and does not require the use of a null modem cable.

Getting Started

Configuring the Phone Preferences

The **IP address:** entry field default is `localhost:6416`. This option is available when Serial Port is set to **TCP/IP**. You can indicate host and port number that the Palm OS Emulator is to connect to. Virtual Phone must use the same settings. See “[Connection Setup Dialog Box](#)” on page 51 for more information.

The other settings (**Redirect Netlib calls to host TCP/IP**, **Sounds**, **Closing/Quitting**, and **HotSync® User Name**) are described in the book *Using Palm OS Emulator*.

Configuring the Phone Preferences

To verify that the Palm OS Emulator is configured to communicate with a GSM Phone, run the **Prefs** application on Emulator, as shown in [Figure 2.3](#).

Figure 2.3 Prefs Application



Prefs

Phone Settings in the Prefs Application

Select **Phone** from the Prefs application’s pop-up list as shown in [Figure 2.4](#).

Figure 2.4 Selecting Phone Preferences



Select the **Connection** pop-up trigger and choose **Serial to GSM Phone**, as shown in [Figure 2.5](#)

Figure 2.5 Selecting the Serial to GSM Phone Connection



Remember that in order to use Virtual Phone you must select the Standard GSM Phone Driver.

Getting Started

Configuring the Phone Preferences

Using Virtual Phone

Virtual Phone is a standard Windows NT/2000 application. This application displays a log of AT Commands that correspond to the Telephony Manager functions which were called by the application executing in Palm OS Emulator.

Every time a Palm OS[®] application calls a Telephony Manager function, the Telephony Manager issues one or more AT commands which are then sent to Virtual Phone. When Virtual Phone receives these AT commands it responds exactly like a real phone.


This chapter explains how you can use the Virtual Phone user interface to test your telephony applications.

- [“Virtual Phone Window”](#)
- [“Service Configuration Dialog Box”](#) on page 17
- [“Response Preferences Dialog Box”](#) on page 43
- [“Connection Setup Dialog Box”](#) on page 51
- [“Speech Calls Dialog Box”](#) on page 53
- [“Short Message Dialog Box”](#) on page 55

Virtual Phone Window

The Virtual Phone window, as shown in [Figure 3.1](#), displays the text equivalent of the original Telephony Manager function, while the actual AT commands or traces are stored in the file `VPAppATLog.log`.

Figure 3.1 Virtual Phone Window



This window displays the Telephony Manager functions that are called and the results of the calls.

File Menu

Select **File** to print the contents the Virtual Phone window or to save the contents to a file.

Edit Menu

Select Edit to manipulate the contents of the Virtual Phone window (Cut, Copy, Paste, etc.). Select **Edit > Clear Log Windows** to delete the text in the log windows.

View Menu

Select **View** to change the characteristics of the Virtual Phone window.

Toolbar Select to display the command icons in the toolbar.

Status Bar Select to show the status bar at the bottom of the window.

AT Command Log

Select to open the AT Command Log window.


Disable Log

Select to disable logging.

Tools Menu

The **Tools** menu, shown in [Figure 3.2](#), provides access to several services.

Figure 3.2 Virtual Phone Tools Menu



Service Configuration

Select to open the Service Configuration dialog box to establish and display the basic services of Virtual Phone. See “[Service Configuration Dialog Box](#)” on page 17 for more information.

Responses Preferences

Select to define the Virtual Phone services, error numbers, and messages. See “[Response Preferences Dialog Box](#)” on page 43 for more information.

Connection Setup

Select to specify the configuration of communication parameters. See “[Connection Setup Dialog Box](#)” on page 51 for more information.

Reconnect

Select to connect Virtual Phone to Palm OS Emulator using the current configuration.

Speech Calls

Select to display voice call information. See “[Speech Calls Dialog Box](#)” on page 53 for more information.

Short Message

Select to open the Short Message dialog box. Use the Short Message dialog box to manage sent and received SMS messages, and to create SMS messages with all configurable options established in the GSM standard. See “[Short Message Dialog Box](#)” on page 55 for more information.

To view the SMS settings, open the SMS tab of the Service Configuration dialog box. See “[SMS Tab](#)” on page 33 for information on the SMS tab of the Service Configuration dialog box.

Send AT Commands

Select to open a dialog box where you can enter AT unsolicited results that you want to send.

Service Configuration Dialog Box


Use the Service Configuration dialog box to set most of the features of Virtual Phone. To open the Service Configuration dialog box, select **Tools > Service Configuration**. The Service Configuration dialog box displays a notebook control with the following tabs:

- [General Tab](#)
- [Network Tab](#)
- [Phone Books Tab](#)
- [Security Tab](#)
- [SMS Tab](#)
- [SIM Tab](#)
- [Speech Tab](#)
- [GPRS Tab](#)

General Tab

The **General Tab**, shown in [Figure 3.3](#), provides access to basic Virtual Phone configuration parameters.

Figure 3.3 Service Configuration's General Tab



Virtual Phone stores these values in the `VPAppcfg.db` file, in the `INF` section. See the Information, Power, and Configuration Services in *Palm OS Programmer's API Reference* for further details.

Phone Settings

Enter the information for the phone you want to emulate.

Brand	Enter any name (limited to 30 alphanumeric characters). Use the function <code>TelInfGetInformation</code> to access this information. See <code>VPAppCfg.db</code> file, INF section, variable name <code>Brand</code> and the <code>TelInfGetInformation</code> function in <i>Palm OS Programmer's API Reference</i> .
Model	Enter any model number (limited to 30 alphanumeric characters). Use the function <code>TelInfGetInformation</code> to access this information. See <code>VPAppCfg.db</code> file, INF section, variable name <code>Model</code> and the <code>TelInfGetInformation</code> function in <i>Palm OS Programmer's API Reference</i> .
Revision	Enter the revision number (limited to 30 alphanumeric characters). Use the function <code>TelInfGetInformation</code> to access this information. See <code>VPAppCfg.db</code> file, INF section, variable name <code>Revision</code> and the <code>TelInfGetInformation</code> function in <i>Palm OS Programmer's API Reference</i> .
Number	Enter the Phone Number (limited to 30 alphanumeric characters) of the “virtual” mobile phone. See <code>VPAppCfg.db</code> file, CFG section, variable name <code>Smscenter</code> and the <code>TelCgfGetPhoneNumber</code> function in <i>Palm OS Programmer's API Reference</i> .
Serial Number	Enter the serial number of the phone you are emulating.

Power

Enter the power information for the phone you are emulating.

Phone Functionality Value

Enter a number indicating the phone functionality status as defined in ETSI standard (see AT+CFUN command).

Battery Status

Enter the battery conditions you are testing.

Battery Powered

Select to indicate that the battery is present and that the Battery Level setting should be taken into consideration.

Battery Not Powered

Select to indicate that the battery is present but its power level is zero.

No Battery

Select to indicate that no battery is present.

See `VPAppCfg.db` file, POW section, variable name `Stat` and see `TelPowGetBatteryStatus` in *Palm OS Programmer's API Reference*.

Battery Level

Select the battery range from 0% (for no power) to 100% (for full power). See `VPAppCfg.db` file, POW section, variable name `Level`. See `TelPowGetPowerLevel` in *Palm OS Programmer's API Reference*.

Sound

Enter the sound information for the phone you are emulating.

Mute

Select to indicate whether the telephone is muted.

Speaker Level

Select to indicate the speaker volume on a scale of 1 to 10, with 1 being soft and 10 being loud.

Network Tab

Use the **Network Tab**, shown in [Figure 3.4](#), to set properties to simulate network-oriented services, including authorized networks, forbidden networks, current network, signal strength, and search mode.

Figure 3.4 Service Configuration's Network Tab

The screenshot shows the 'Service Configuration' dialog box with the 'Network' tab selected. The 'Current List' is set to 'Available Networks'. Below this is a table of available networks:

SimId	Id	Short Name	Name
1	20201	C-OTE	COSMOTE
2	20205	PAN	PANAFON
3	20210	TLSTET	TELESTET
4	20404	LIBTEL	LIBERTEL

Below the table, the 'State' is set to 'Available' and the 'ME Reg State' is set to '1 - Registered'. The 'Network Parameters' section includes 'Search Mode' (Manual selected), 'Signal Strength' (Not detectable checked, value 15), 'Location' (Cell Id: 00AD, Area Code: 00C3), and 'Network Registration Notification' (State: 2 - Network Reg. & Location Info, Send Notif. button).

Virtual phone stores these values in the `VPAppcfg.db` file in the `NWK` section. See the Telephony Network section in the *Palm OS Programmer's Companion*, vol. II, *Communications* for further details.

Networks

Specify the networks for your phone.

Current List

Select a list of network from either the **Available Networks** list or the **Preferred Networks** list. Select **Modify List** to display the Network List Management dialog box.

A network is defined by its **SimId**, **Id**, **Short Name** and **Name**. Virtual Phone stores these values in the `AvailableNwk.db` file. See `AvailableNwk.db` file, in the NWK section, variable name `Num`. See `TelNwkGetNetworks` in *Palm OS Programmer's API Reference*.

SimId

The order number of the operator in the SIM available/preferred operator list.

Id This is a numeric value with a maximum length of 4 characters. See the `AvailableNwk.db` or `PreferredNwk.db` file, in the NWK section, variable name `Id`. See `TelNwkGetNetworks` in *Palm OS Programmer's API Reference*.

Short Name

An abbreviation of the **Name** with a maximum 8 alphanumeric characters. See the `AvailableNwk.db` or `PreferredNwk.db` file, in the NWK section, variable name `Sname`.

Name

An alphanumeric value of 16 characters. See the `AvailableNwk.db` or `PreferredNwk.db` file, in the NWK section, variable name `Lname`. See `TelNwkGetNetworks` in *Palm OS Programmer's API Reference*.

See `TelNwkGetNetworks` in *Palm OS Programmer's API Reference*.

State Select the state of the network that is selected in the table. There are four options:

Unknown

Select this value if the network unknown (Stat=0).

Available

Select this value if the selected network is available (Stat=1).

Current

Select this value if the highlighted network is currently selected (Stat=2).

Forbidden

Select this value if the network is unavailable for security reasons (Stat=3).

See the `AvailableNwk.db` or `PreferredNwk.db` file, in the NWK section, variable name `Stat`. See `TelNwkSelectNetwork` in *Palm OS Programmer's API Reference*.

ME Reg State Select the ME (Mobile Equipment, that is the GSM phone) network registration status.

1 - Registered

Select this value if the highlighted network is registered to a provider (RegStat=1).

2 - Not Registered, ME Not searching

Select this value if the network is not registered (RegStat=2).

3 - Registration Denied

Select this value if the network is secured and registration is rejected (RegStat=3).

4 - Unknown


Select this value if the network is not recognized by Virtual Phone (RegStat=4).

5 - Registered, Roaming

Select this value if the network is registered as roaming (RegStat=5).

See `VPAppCfg.db` file, in the `NWK` section, variable name `RegStat`. See `TelNwkGetNetworkName` in *Palm OS Programmer's API Reference*.

Note: There is only one Current network. If a network is set to Current, then the state of the former current is set to Unknown. Furthermore, you will not be able to save the settings of the Network Service if there is no current network. If you try to save the Network Serve settings when there is no current network, you will see this message:



The list of available networks is stored in the file `AvailableNwk.db` and is accessible as an ASCII text file.

Network Parameters

Set the parameters for the network you are emulating.

Search Mode Select how you want Virtual Phone to select a network.

Manual

Select this value if you want Virtual Phone to manually select a network

Auto

Select this value if you want Virtual Phone to automatically select a network.

See `VPAppcfg.db` file, in the NWK section, variable name `SearchMd`. See `TelNwkGetSearchMode` in *Palm OS Programmer's API Reference*. See `kTelNwkManualSearch` in *Palm OS Programmer's API Reference*.

Location

Set the location information for the current cell and its area code.

Cell Id

Enter the value of the current Cell (limited to 2 alphanumeric characters). See `VPAppCfg.db` file, in the NWK section, variable name `CellId`. See `TelNwkGetLocation` in *Palm OS Programmer's API Reference*.

Area Code

Enter the value of the Cell's area code (limited to 2 alphanumeric characters). See `VPAppCfg.db` file, in the NWK section, variable name `AreaCd`. See `TelNwkGetLocation` in *Palm OS Programmer's API Reference*.

Network Registration Notification State

Set the network registration notification state.

0 - None

Select this value to disable the network registration unsolicited results code.

1 - Network Reg.

Select this value to enable the network registration unsolicited results code.

2 - Network Reg. & Location Info

Select this value to enable the network registration and location information unsolicited results code.

Send Notif. button

Click to send a network registration notification.

Signal Strength

Set the signal level you want to test.

Not detectable

If checked, Virtual Phone will issue a 99 for Signal Strength. As specified in the GSM Technical Specification. See *VPAppCfg.db* file, in the NWK section, variable name `SigLev`. See `TelNwkGetSignalLevel` in *Palm OS Programmer's API Reference*.

Entry field

Enter a numeric value between 0 and 31, with 0 being no signal and 31 being the maximum signal strength. See *VPAppCfg.db* file, in the NWK section, variable name `SigLev`. See `TelNwkGetSignalLevel` in *Palm OS Programmer's API Reference*.

Phone Books Tab

Use the Phone Books tab, shown in [Figure 3.5](#), to display the list of all the stored phone book names and their associated phone numbers.

Figure 3.5 Service Configuration's Phone Books Tab

Service Configuration

Security SMS SIM Speech GPRS

General Network Phone Books

General

Maximum Name Length : 10

Phone Books

Name	Status	Used Entries	Total Entries
DC	On	0	100
EN	On	0	100
FD	On	0	100
LD	On	0	100
MC	On	0	100
ME	On	0	100
MT	On	0	100
ON	On	1	5
RC	On	0	100
SM	On	0	100
TA	On	0	100

☒ Activated
☒ Current Phone Book
☐ PIN2 protected

Total Entries: 100
Used Entries: 0

OK Cancel Apply

Maximum Name Length

Enter the maximum length of a name associated to a phone number. A maximum of 30 characters is permitted for the name length.

See the `VPAppCfg.db` file in the PHB section, variable name `MaxNameLen`. See `TelPhbGetEntryMaxSizes` in *Palm OS Programmer's API Reference*.

Phone Books

Display information about the stored phone books.

Activated Check to indicate that the phone book is present.

Current Phone Book

The currently selected Phone Book is stored in the `VPAppCfg.db` file in the PHB section, variable name `Selbook`. See `VPAppCfg.db` file in the PHB section, variable name `Selbook` for the currently selected phone book. See `TelPhbGetSelectedPhonebook` in *Palm OS Programmer's API Reference*.

PIN2 protected As defined in the ETSI standard, the FD phonebook can be protected. Check to indicate that the FD phonebook is protected.

Total Entries Enter the maximum number of entries allowed in the phone book.

Used Entries Enter the number of entries used in the phonebook.

For all of the above see `TelPhbGetAvailablePhonebooks` in *Palm OS Programmer's API Reference*.

Security Tab

Use the **Security Tab**, shown in [Figure 3.6](#), to simulate a mobile phone's security system.

Figure 3.6 Service Configuration's Security Tab

The screenshot shows the 'Service Configuration' dialog box with the 'Security' tab selected. The dialog has a title bar with a close button. Below the title bar are tabs for 'General', 'Network', 'Phone Books', 'Security', 'SMS', 'SIM', 'Speech', and 'GPRS'. The 'Security' tab is active, showing settings for SIM and Phone security. The 'SIM' section includes fields for PIN Code 1, PIN Code 2, PUK Code 1, and PUK Code 2, all set to '0000'. There is a 'Facility Lock' checkbox labeled 'Lock SIM Card' which is checked. The 'Phone' section includes a 'Phone Code' field set to '0000' and two 'Facility Lock' checkboxes: 'Lock Phone to SIM card' (unchecked) and 'Lock Phone to first inserted SIM card' (unchecked). The 'Security Status' section has a 'Ready' radio button selected, and several other radio buttons for 'PIN1 expected', 'PIN2 expected', 'Phone to SIM expected', 'PUK1 expected', 'PUK2 expected', and 'Phone to First SIM expected'. At the bottom are 'OK', 'Cancel', and 'Apply' buttons.

The values entered and displayed here are stored in the `VPAppCfg.db` file in the `STY` section.

You can change the values of these codes using Telephony Manager functions or directly in this dialog box. To change an authentication code, see `TelStyChangeAuthenticationCode` in *Palm OS Programmer's API Reference*.

SIM

Enter the security information for the SIM card.

PIN Code 1 Enter the primary Personal Identification Number (PIN), (four digits maximum). See `VPAppCfg.db` file in the STY section, variable name `PIN1`. See `TelStyEnterAuthenticationCode` in *Palm OS Programmer's API Reference*.

Lock SIM Card Check to activate PIN Code 1.

PIN Code 2 Enter the secondary Personal Identification Number (four digits maximum). See `VPAppCfg.db` file in the STY section, variable name `PIN2`. See `TelStyEnterAuthenticationCode` in *Palm OS Programmer's API Reference*.

PUK Code 1 Enter the primary Personal Universal Key (PUK) (four digits maximum). See `VPAppCfg.db` file in the STY section, variable name `PUK`. See `TelStyEnterAuthenticationCode` in *Palm OS Programmer's API Reference*.

PUK Code 2 Enter the secondary Personal Universal Key (PUK) (four digits maximum). See `VPAppCfg.db` file in the STY section, variable name `PUK2`. See `TelStyEnterAuthenticationCode` in *Palm OS Programmer's API Reference*.

Phone Code Enter the Phone to Subscriber Identification Module (SIM) code (four digits maximum). See `VPAppCfg.db` file in the STY section, variable name `Phone`. See `TelStyChangeAuthenticationCode` in *Palm OS Programmer's API Reference*.

Lock Phone SIM Card
Check to activate the Phone Code.

Phone to First SIM Code

Enter the Phone to first SIM card password.

Lock Phone to first inserted SIM Card

Check to activate the Phone to First SIM Code.

Security State

Enter the security state of the phone. See `VPAppCfg.db` file in the STY section, variable name `State`. See `TelStyGetAuthenticationState` in *Palm OS Programmer's API Reference*.

Ready

Select this value if Virtual Phone is ready to receive AT commands. `State=0`. See `VPAppCfg.db` file in the STY section, variable name `State`. See `kTelStyReady` in *Palm OS Programmer's API Reference*.

PIN1 Select this value to indicate that Virtual Phone should expect a primary Personal Identification Number (PIN). `State=1`. See `VPAppCfg.db` file in the STY section, variable name `State`. See `kTelStyPin1CodeId` in *Palm OS Programmer's API Reference*.

PUK1

Select this value to indicate that Virtual Phone should expect the primary Personal Universal Key (PUK). `State=3`. See `VPAppCfg.db` file in the STY section, variable name `State`. See `kTelStyPuk1CodeId` in *Palm OS Programmer's API Reference*.

Phone to SIM expected

Select this value to indicate that Virtual Phone should expect the Phone to Subscriber Identification Module (SIM) code. `State=5`. See `VPAppCfg.db` file in the STY section, variable name `State`.

See `kTelStyPhoneToSimCodeId` in *Palm OS Programmer's API Reference*.

PIN2 Select this value to indicate that Virtual Phone should expect a secondary Personal Identification Number (PIN).
State=2. See `VPAppCfg.db` file in the STY section, variable name `State`. See `kTelStyPin2CodeId` in *Palm OS Programmer's API Reference*.

PUK2

Select this value to indicate that Virtual Phone should expect the secondary Personal Universal Key (PUK).
State=4. See `VPAppCfg.db` file in the STY section, variable name `State`. See `kTelStyPuk2CodeId` in *Palm OS Programmer's API Reference*.


Phone to First SIM expected

Select this value to indicate that Virtual Phone should expect the Phone to First SIM Key (PH-FSIM PIN).

SMS Tab

Use the **SMS Tab** to set SMS features.

Figure 3.7 Service Configuration's SMS Tab



The values entered and displayed here are stored in the `VPAppCfg.db` file in the SMS section (except for **Call Center** which is stored in the CFG section) and in the SMS (Short Message Services) files, `SmsStore.db` and `SmsStoreSend.db`.

Call Center

Enter the phone's service center. See `VPAppCfg.db` file in the CFG section, variable name `SmsCenter`. See `TelCfgSetSmsCenter` in *Palm OS Programmer's API Reference*.

Max SMS Index Enter the maximum number of messages to display and store (maximum 500). See the VAppCfg.db file in the SMS section, variable name MaxEntries. See TelSmsGetMessageCount in *Palm OS Programmer's API Reference*.

Service for MO SMS Messages

Specify the service or service preference that the MT (Mobile Terminated phone) will use to send MO (Mobile Originated phone) SMS messages.

0 - GPRS


1 - Circuit Switched

2- GPRS Preferred (use circuit switched if GPRS not available)

SIM Tab

Use the SIM tab to set SIM properties for the phone you are emulating.

Figure 3.8 Service Configuration's SIM Tab



IMSI - International Subscriber Identity

Enter the international mobile subscriber identity number corresponding to the SIM card.

Voice Mail Number

Enter the voice mail number for the SIM card.

Voice Mail Name Enter the voice mail name for the SIM card.


Sim Card - Sim Inserted

Select this setting to indicate whether the SIM card is in use for the emulation.

Speech Tab

Use the Speech tab to set properties for speech calls.

Figure 3.9 Service Configuration's Speech Tab



Connected Line Identification Presentation

TA

Check to show the result code presentation status in the Terminal Adapter (TA) phone book.

Nwk

Check to show the subscriber connected line identification presentation service status in the network phone book.

Calling Line Identification Presentation

TA

Check to show the result code presentation status in the Terminal Adapter (TA) phone book.

Nwk

Check to show the subscriber connected line identification presentation service status in the network phone book.

Calling Line Identification Restriction

Subscription

Set according to the subscription of the calling line identification restriction service.

On Network

Set to the subscriber calling line identification restriction service status in the network.

Emergency Call Number

Set to the emergency mobile phone number.

Call forwarding by class - Select the class of information:

Voice - Select this option for telephony services.

Data - Select this option for all bearer services.

Fax - Select this option for facsimile services.

Sms - Select this option for short message services.

Data Circuit Sync - Select this option for synchronous data service.

Data Circuit Async - Select this option for asynchronous data service.

Dedicated Packet Access - Select this option for dedicated packet access service.

Dedicated PAD Access - Select this option for dedicated PAD access service.

Call forwarding by class - Select the reason for call forwarding:

Unconditional - Select this option to forward always.

Busy - Select this option to forward when the line is busy.

No Reply - Select this option to forward when there is no reply.

Not Reachable - Select this option to forward when the line is not reachable.

All Call Fwd - Select this option for all call forwarding. (See GSM 2.30[19].)

Cond. Call Fwd - Select this option for conditional call forwarding. (See GSM 2.30[19]).

Active Check to indicate that call forwarding is active.

Number Enter the phone number of the forwarding address.

Time Enter the time in seconds to wait before call is forwarded.

Sub Addr Enter the call forwarding subaddress.

Facility lock	<p>Select the class of information. Call barring facilities are based on GSM supplementary services (refer GSM 02.88 [6]). The interaction of these with other commands is based on other GSM supplementary services as described in the GSM standard.</p> <p>See the selection descriptions in the Call forwarding by class section above.</p>
Facility lock	<p>Select the facility from the list:</p> <ul style="list-style-type: none">- Bar All Outgoing calls - (AO)- Bar Outgoing International calls - (OI)- Bar Outgoing international calls eXcept to home country - (OX)- Bar All Incoming Calls - (AI)
Facility Lock Status	<p>Select this value to indicate whether the facility lock is active.</p>
Password	<p>Enter the facility lock password.</p>
FD Facility Lock Status	<p>Select this value to indicates whether the FD facility lock is active.</p>

GPRS Tab

Use the GPRS tab to set GPRS properties for the phone you are emulating.

Figure 3.10 Service Configuration's GPRS Tab

Service Configuration

General | Network | Phone Books | Security | SMS | SIM | Speech | **GPRS**

GPRS Network Registration Status: 1 - Registered

PDP (Max 5)

CId	APN	State	Requested QOS	Minimum QOS
1	MyAPN	0	0,0,0,0,0	0,0,0,0,0

Parameters

CId: 1

PDP Type: IP

APN: MyAPN

Address: 123.123.123.1

Compression

Header ☐ Data ☐

Action

Delete

Add PDP

Activate

Deactivate

Notif.

Reject React Deact Detach Class

Location

Cell Id: 00AD

Area Code: 00C3

Network Registration Notification

2 - Network Reg. & Location Info

Send Notif.

OK Cancel Apply

GPRS Network Registration Status

Set the registration status for the GPRS features.

0 - Not Registered, ME Not Searching (ME stands for Mobile Equipment, referring to a GSM phone)

1 - Registered


	2 - Not Registered, ME searching
	3 - Registration Denied
	4 - Unknown
	5 - Registered, Roaming
PDP	<p>Lists the Packet Data Protocol information. You can specify at most five PDPs.</p> <p>CId - Shows the PDP Context Identifier, a numeric parameter which specifies a particular PDP context definition. The parameter is local to the TE-MT interface and is used in other PDP context-related commands. (TE stands for Terminal Equipment, referring to a computer; MT stands for Mobile Terminated, referring to something received on a mobile phone.)</p> <p>APN - Shows the Access Point Name.</p> <p>State - Shows the PDP context status: either activated or deactivated.</p> <p>Requested QOS - Shows the requested Quality of Service Profile.</p> <p>Minimum QOS - Shows the minimum acceptable Quality of Service Profile.</p>
CId	Enter the PDP Context Identifier.
Compression	<p>Select the compression you want to enable.</p> <p>Header</p> <p style="padding-left: 40px;">Check to enable PDP header compression.</p> <p>Data</p> <p style="padding-left: 40px;">Check to enable PDP data compression.</p>
PDP Type	Select the type of packet data protocol: IP, PPP, or OSPIH.
APN	Enter the access point name.
Address	Enter the MT (Mobile Terminated) address for the PDP.

PD1	Specific to the PDP type.
PD2	Specific to the PDP type.
PD3	Specific to the PDP type.
Action buttons	
	Delete - Select an item in the PDP table, and click to delete the PDP.
	Add PDP - Click to add a new PDP.
	Activate - Click to activate the selected PDP.
	Deactivate - Click to deactivate the selected PDP.
Notif. buttons	
	Reject - Click to send a reject notification.
	React - Click to send a reactivation notification.
	Deact - Click to send a deactivation notification.
	Detach - Click to send a detach notification.
	Class - Click to send a change of class notification.
Location Cell Id	Enter a two-byte cell ID in hexadecimal format.
Location Area Code	
	Enter a two-byte location area code in hexadecimal format.
Location Network Registration Notification Code	
	0 - None
	1 - Network Reg.
	2 - Network Reg. & Location Info
Send Notif. button	
	Click to send a notification.

Response Preferences Dialog Box

To open the Response Preferences dialog box, select **Tools > Response Preferences**. Use this screen to select an error which will systematically be returned by a service.

Figure 3.11 Response Preferences Dialog Box



The following list associates a Virtual Phone service to a Telephony Manager function as supported by a standard GSM phone driver.

Table 3.1 Virtual Phone Services and Telephony Manager Functions

Services	Associated Functions
Accept Call	TelSpcAcceptCall
Add Entry	TelPhbAddEntry
Auto Operator Select	TelNwkSetSearchMode
Call Number	TelSpcCallNumber
Change Authentication Code	TelStyChangeAuthenticationCode
Close Line and Reject Call	TelSpcCloseLine or TelSpcRejectCall
Delete Entry	TelPhbDeleteEntry

Table 3.1 Virtual Phone Services and Telephony Manager Functions <E.Emphasis>(continued)

Services	Associated Functions
Delete Message	TelSmsDeleteMessage
Enter Authentication Code	TelStyEnterAuthentication
Get Authentication State	TelStyGetAuthenticationState
Get Available Storage	TelSmsGetAvailableStorage
Get Available Phone Books	TelPhbGetAvailablePhonebook
Get Battery State	TelPowGetBatteryStatus
Get Brand Number	TelInfGetInformation
Get Call State	TelGetCallState
Get Entries	TelPhbGetEntries
Get Entry Max Sizes	TelPhbGetEntryMaxSizes
Get Location	TelNwkGetLocation
Get Model Number	TelInfGetInformation
Get Networks	TelNwkGetNetworks
Get Phone Number	TelCgfGetPhoneNumber
Get Revision	TelInfGetInformation
Get Selected Phone Book	TelPhbGetSelectedPhonebook
Get Selected Network	TelNwkGetSelectedNetwork
Get Selected Storage	TelSmsGetSelectedStorage
Get Signal Level	TelNwkGetSignalLevel
Get Sms Center	TelCgfGetSmsCenter

Table 3.1 Virtual Phone Services and Telephony Manager Functions <E.Emphasis>(continued)

Services	Associated Functions
Delete Message	TelSmsDeleteMessage
Enter Authentication Code	TelStyEnterAuthentication
Get Authentication State	TelStyGetAuthenticationState
Get Available Storage	TelSmsGetAvailableStorage
Get Available Phone Books	TelPhbGetAvailablePhonebook
Get Battery State	TelPowGetBatteryStatus
Get Brand Number	TelInfGetInformation
Get Call State	TelGetCallState
Get Entries	TelPhbGetEntries
Get Entry Max Sizes	TelPhbGetEntryMaxSizes
Get Location	TelNwkGetLocation
Get Model Number	TelInfGetInformation
Get Networks	TelNwkGetNetworks
Get Phone Number	TelCgfGetPhoneNumber
Get Revision	TelInfGetInformation
Get Selected Phone Book	TelPhbGetSelectedPhonebook
Get Selected Network	TelNwkGetSelectedNetwork
Get Selected Storage	TelSmsGetSelectedStorage
Get Signal Level	TelNwkGetSignalLevel
Get Sms Center	TelCgfGetSmsCenter

Table 3.1 Virtual Phone Services and Telephony Manager Functions <E.Emphasis>(continued)

Services	Associated Functions
Delete Message	TelSmsDeleteMessage
Enter Authentication Code	TelStyEnterAuthentication
Get Authentication State	TelStyGetAuthenticationState
Get Available Storage	TelSmsGetAvailableStorage
Get Available Phone Books	TelPhbGetAvailablePhonebook
Get Battery State	TelPowGetBatteryStatus
Get Brand Number	TelInfGetInformation
Get Call State	TelGetCallState
Get Entries	TelPhbGetEntries
Get Entry Max Sizes	TelPhbGetEntryMaxSizes
Get Location	TelNwkGetLocation
Get Model Number	TelInfGetInformation
Get Networks	TelNwkGetNetworks
Get Phone Number	TelCgfGetPhoneNumber
Get Revision	TelInfGetInformation
Get Selected Phone Book	TelPhbGetSelectedPhonebook
Get Selected Network	TelNwkGetSelectedNetwork
Get Selected Storage	TelSmsGetSelectedStorage
Get Signal Level	TelNwkGetSignalLevel
Get Sms Center	TelCgfGetSmsCenter

Table 3.1 Virtual Phone Services and Telephony Manager Functions <E.Emphasis>(continued)

Services	Associated Functions
Delete Message	TelSmsDeleteMessage
Enter Authentication Code	TelStyEnterAuthentication
Get Authentication State	TelStyGetAuthenticationState
Get Available Storage	TelSmsGetAvailableStorage
Get Available Phone Books	TelPhbGetAvailablePhonebook
Get Battery State	TelPowGetBatteryStatus
Get Brand Number	TelInfGetInformation
Get Call State	TelGetCallState
Get Entries	TelPhbGetEntries
Get Entry Max Sizes	TelPhbGetEntryMaxSizes
Get Location	TelNwkGetLocation
Get Model Number	TelInfGetInformation
Get Networks	TelNwkGetNetworks
Get Phone Number	TelCgfGetPhoneNumber
Get Revision	TelInfGetInformation
Get Selected Phone Book	TelPhbGetSelectedPhonebook
Get Selected Network	TelNwkGetSelectedNetwork
Get Selected Storage	TelSmsGetSelectedStorage
Get Signal Level	TelNwkGetSignalLevel
Get Sms Center	TelCgfGetSmsCenter

Table 3.1 Virtual Phone Services and Telephony Manager Functions <E.Emphasis>(continued)

Services	Associated Functions
Hold Line	TelSpcHoldLine
Mute	TelSndMute
Operator Select	TelNwkSelectNetwork
Read Message	TelSmsReadMessage
Read Messages	TelSmsReadMessages
Select Phone Book	TelPhbSelectPhonebook
Select Storage	TelSmsSelectStorage
Send Burst DTMF	TelSpcSendBurstDTMF
Send Short Message	TelSmsSendMessage
Set Sms Center	TelCgfSetSmsCenter

Response Configuration

According to Phone's State

Select this option to return a value according to the current state of Virtual Phone.

Reply with Error

Use this option to return the selected error message.

Table 3.2 GSM Errors

GSM Error Number	Error	Telephony Constant
0	Phone failure	telErrCommandFailed
1	Noconnection to phone	telErrPhoneComm

Table 3.2 GSM Errors <E.Emphasis>(continued)

GSM Error Number	Error	Telephony Constant
2	Phone- adapter link reserved	telErrPhoneComm
3	Operation not allowed	telErrCommandFailed
4	Operation not supported	telErrFeatureNotSupported
5	PH-SIM PIN required	telErrPhoneToSIMPINRequired
10	SIM not inserted	telErrNoSIMInserted
11	SIM PIN required	telErrPINRequired
12	SIM PUK required	telErrPUKRequired
13	SIM failure	telErrSIMFailure
14	SIM busy	telErrSIMBusy
15	SIM wrong	telErrSIMWrong
16	Incorrect password	telErrPassword
17	SIM PIN2 required	telErrPIN2Required
18	SIM PUK2 required	telErrPUK2Required
20	Memory full	telErrPhoneMemAllocation
21	Invalid index	telErrInvalidIndex

Table 3.2 GSM Errors <E.Emphasis>(continued)

GSM Error Number	Error	Telephony Constant
22	Not found	telErrEntryNotFound
23	Memory failure	telErrPhoneMemFailure
24	Text string too long	telErrInvalidString
25	Invalid characters in text string	telErrInvalidString
26	Dial string too long	telErrInvalidDial
27	Invalid characters in dial string	telErrInvalidDial
30	No network service	telerrNonetwork
31	Network time-out	telErrNetworkTimeOut
100	Unknown	telErrUnknown


This will load the default value which is **Reply according to Virtual Phone's state** for all of the service functions.

Connection Setup Dialog Box

Use the Connection Setup dialog box to select and modify the communication parameters. To open the Connection Setup dialog box, select **Tools > Connection Setup**. The values assigned in this window must match the values assigned in Palm OS Emulator (See [“Configuring Palm OS Emulator”](#) on page 7).

The values entered and displayed here are stored in the `VPAppCfg.db` file in the TDP and Serial sections.

Figure 3.12 Connection Setup Dialog Box



TCP Port Number If you select TCP, you must provide a Port Number. This number must match the number assigned to Palm OS Emulator. See [“Configuring Palm OS Emulator”](#) on page 7 for more information. See the `VPAppCfg.db` file, in the TCP section, variable name `Port`.

Serial

Select Serial to permit access to the parameters which configure serial communication. Virtual Phone's defaults are the same as Palm OS Emulator's defaults. It is best to retain these default values. See the `VPAppCfg.db` file in the Serial section. The variable names are `Port`, `BaudRate`, `StopBit`, `Parity`, `FlowCtl` and `DataBit`.

Fixing Connection Problems


Virtual Phone may not be able to establish a connection for several reasons. For example, the specified serial port in the **Connection Dialog Box** may already be in use.

If a connection cannot be established, Virtual Phone displays a message box (see [Figure 3.13](#)) and activates the **Connection** icon in the tool bar (as illustrated below in [Figure 3.14](#)).

Figure 3.13 Connection Error Message Dialog Box



Figure 3.14 Connection Tool Bar Icon



You can then either close the application that is preventing the connection and click the reconnect icon, or you can use the **Tools > Reconnect** menu. As an alternative, you can go back to the Connection Setup dialog box and change the connection settings.

When the connection icon is dimmed, the serial port is successfully open (if serial communications was selected). If TCP

communication was selected, then Virtual Phone is waiting for a connection on the specified port number.

Speech Calls Dialog Box

Use the **Speech Calls Dialog Box** to display current voice communication and their parameters, and to simulate incoming voice calls. To open the Speech Calls dialog box, select **Tools > Speech Calls**.

Figure 3.15 Speech Calls Dialog Box

Type	Line ID	Other party number	Status

Incoming Calls

New Incoming Call

When selected Virtual Phone simulates an incoming voice call.

ID Available

If checked and a value is entered in the associated edit field, this value will appear in the **Other party number**

column of the **Open lines** list and will be sent to the Palm OS Emulator. The Id of a caller is not sent unless the **ID Available** check box is checked.

Possible Operations

	This is relevant to an open line.
Connect	Establish a connection and accept the Outgoing call. See <code>TelSpcAcceptCall</code> in <i>Palm OS Programmer's API Reference</i> . See <code>sysTelSpcLaunchCmdCallConnect</code> notification in <i>Palm OS Programmer's API Reference</i> .
Release	Release the line and hang-up the phone. See <code>TelSpcCloseLine</code> in <i>Palm OS Programmer's API Reference</i> . See <code>sysTelSpcLaunchCmdCallReleased</code> notification in <i>Palm OS Programmer's API Reference</i> .
Busy	Respond to the Outgoing call with a busy signal. See <code>TelSpcRejectLine</code> in <i>Palm OS Programmer's API Reference</i> . See <code>sysTelSpcLaunchCmdCallBusy</code> notification in <i>Palm OS Programmer's API Reference</i> .

NOTE: Virtual Phone does support Conference calls and Reports.

Short Message Dialog Box

Use the **Short Message Dialog Box** to create SMS messages, to view stored SMS messages, and to view a history of sent SMS messages.

Figure 3.16 Short Message Dialog Box

The screenshot shows the 'Short Message' dialog box with the 'Encode/Decode a SMS' tab selected. The 'PDU' field is empty. The 'Direction' is set to 'Incoming SMS (SC to MS)'. The 'SMS Center' section has a checkbox 'SMS Center is configured in MS' which is unchecked, and an 'Address' field with the value '+336534985'. Below this is a table of message parameters:

Message Type Indicator (MTI)	Deliver
More Messages to Send (MMS)	No More Messages
Reply Path (RP)	No
User Data Header Indicator (UDHI)	No Header
Status Report Indication (SRI)	No Status Report
Originating Address (OA)	
Type Of Numbering (TON)	National number
Numbering Plan Indication (NPI)	ISDN/telephone
Address	+336558986

At the bottom of the dialog are buttons for 'Create PDU', 'Receive PDU', 'OK', 'Cancel', and 'Apply'.

The Short Message dialog box has three tabs:

- [“Encode/Decode an SMS Tab”](#) on page 56
- [“SMS Storage Tab”](#) on page 56
- [“Sent SMS History Tab”](#) on page 58

Encode/Decode an SMS Tab

Use the **Encode/Decode an SMS** tab, shown in [Figure 3.16](#), to create a new SMS delivery message, which is an SMS message received by Virtual Phone from the GSM network. The message is stored in the first available location in the `SmsStore.db` file. To open the Short Message dialog box, select **Tools > Short Message**.

PDU	Enter the PDU (Protocol Data Unit) for this message.
Direction	Select whether this is an incoming message or an outgoing message. Incoming SMS (SC to MS) - Select if this is an incoming message. Outgoing SMS (MS to SC) - Select if this is an outgoing message.
Decode	Click to decode this message.

SMS Center

SMS Center is configured in MS

Check to indicate that the SMS Center is configured in the MS (Mobile Station).

Address Enter the address for the message.

Message Parameters

Enter the other message data in the scrollable table.

Create PDU button

Click to create a PDU.


Receive PDU button

Click to receive a PDU.

SMS Storage Tab

Use the **SMS Storage** tab, shown in [Figure 3.17](#), to view information about stored SMS messages.

Figure 3.17 Short Message's SMS Storage Tab



Messages

Id	The identification number of the message.
Type	The message type.
Multi Part	The SMS is composed of several parts.
Status	Indicates the status of the message: received unread, received read, stored unsent, or stored sent.
Message Text	Content of the SMS message.
Refresh button	Click to refresh the messages table.
Send to network button	


When the SMS message is stored in Virtual Phone but not yet sent, click to send the message to the network.

Delete button Click to delete a selected message.

Sent SMS History Tab

Use the **Sent SMS History** tab, shown in [Figure 3.18](#), to view information about SMS messages that have been sent.

Figure 3.18 Short Message's Sent SMS History Tab



Messages

Id	The identification number of the message.
Multi Part	The SMS is composed of several parts.
Status	Indicates the status of the message: received unread, received read, stored unsent, or stored sent.
Report Status	The SMS contains a status report request.
Message Text	Content of the SMS message.
Refresh List button	Click to refresh the messages table.
Send Report button	Click to send an SMS status report for the selected SMS message (if applicable).
Delete button	Click to delete a selected message.

Log and Database Files

This appendix covers the files that Virtual Phone uses:

- “[Configuration Files](#)” on page 62
 - VAppCfg.db
 - AvailableNwk.db
- “[Phone Book Databases](#)” on page 65
 - PhbDC.db
 - PhbEn.db
 - PhbFD.db
 - PhbLD.db
 - PhbMC.db
 - PhbME.db
 - PhbOn.db
 - PhbRC.db
 - PhbSM.db
 - PhbTA.db
- “[SMS Files](#)” on page 66
 - SmsStore.db
 - SmsStoreSent.db
- “[Log File](#)” on page 69
 - VAppATLog.log

Configuration Files

If the two configuration files are not found in the current directory upon execution, Virtual Phone generates them with the default values. These files, their structure, and their records are described below.

Application Configuration File - VAppCfg.db

The configuration file, VAppCfg.db, stores data relevant to Virtual Phone's Services and their configuration. The file is divided into 12 sections, listed in [Table A.1](#).

Table A.1 VAppCfg.db File Sections

Section Name	Corresponding Services
CFG	Configuration
INF	Phone Information
SPC	Speech Call
POW	Power
NWK	Network
PHB	Phone Book
STY	Security
SMS	Short Message
TCP	TCP
Serial	Serial
ReadThread	Active connection (either TCP or Serial)
Disp	Error Reply Parameters

The following list contains the Service Name and all the variable names associated to the service and the variable default value.

VAppCfg.db

[CFG] Configuration Service

SmsCenter=+336534985	
	SMS Center Number
PhNum=+336558986	
	Virtual Phone's number
[INF]	Information Service
Brand=Virtual Phone Win	
	Virtual Phone's Brand Name
Model=3210	Virtual Phone's Model
Revision=354815	
	Virtual Phone's Revision number
[SPC]	Speech Call Service
EmcNum=112	The emergency call number
[POW]	Power Service
Level=75	Battery power level
Status=0	Battery status
[NWK]	Network Service
SigLev=15	Signal Level
CellId=AD	Cell Id
AreaCd=BC	Area Code
SearchMd=1	Search mode
RegStat=1	Registration state
[PHB]	Phone Book Service
NumBooks=4	Number of phone books (Max=4)
SelBook=0	Selected phone book
MaxEntries=100	Maximum number of entry slots
MaxNameLen=10	Maximum name length
[STY]	Security Service
State=0	security state
Pin=0000	Pin Code

Log and Database Files

Configuration Files

Pin2=0000	PIN2 Code
Puk=0000	PUK Code
Puk2=0000	PUK2 Code
Phone=0000	Phone Code
[SMS]	Short Message Service
MaxEntries=100	Maximum number of message slots
RecSent=0	Receive sent messages
NDelId=2	Next delivery message id
NSubId=2	Next submit message id
[TCP]	TCP Connection
Port=6416	Port number
[Serial]	Serial Connection
Port=COM2	Port to open
BaudRate=19200	Baud rate
StopBit=1	Number of stop bits
Parity=None	Parity
FlowCtl=None	Flow control
DataBit=8	Data bit
[ReadThread]	Connection to use
ConType=1	Serial/TCP
[Disp]	Reply Parameters
FR0Id=1	Response type: According to VP state/Error
FE0Id=0	Error number
FR2Id=1	
FE2Id=0	
...	

Available Network File - AvailableNwk.db

The Available Network file, `AvailableNwk.db`, lists the networks available to Virtual Phone. You can modify, add and delete networks using an ASCII text editor (for example, `Notepad`). Remember to change the `Num` key so that it corresponds to the number of networks that you want Virtual Phone to take into account.

The Section Numbers must be consecutive.

AvailableNwk.db

[NWK]

Num=1 The number of available networks.

[1] Section Number

Id=5001 The network's Id

LName=Virtual Phone 1

 The network's long name

SName=VPCom 1 The network's short name

Stat=2 The network's state

[2]

Id=5051

LName=Virtual Phone 2

SName=VPCom 2

Stat=2

Phone Book Databases

You can use the Service Configuration's Phone Books tab to modify Virtual Phone phone book databases. See "[Phone Books Tab](#)" on page 27 for more information.

You can also modify phone books manually using an ASCII text editor. The Last Dialed Phone Book automatically contains the last dialed phone number and any changes to this file will be overridden by Virtual Phone when it dials a number.

See “[Phone Book Files](#)” on page 4 for a list of all of the phone books supported.

Phone Book Database Organization

Phone book databases are organized as follows:

[1] Index of entry

Name= John Name

Tel=+33662685921

Phone Number

[3]

Name= David

Tel=+49656654654

[4]

Name= Marc

Tel=045687654

SMS Files

The SMS (Short Message Services) files, `SmsStore.db` and `SmsStoreSend.db`, are generated by Virtual Phone. They both have the same basic structure and contain all the SMS exchanged between Virtual Phone and the Palm OS Emulator. The difference between the two files are the Delivery and Submit specific data elements.

The values associated to a data elements are valid for version 1.0 of Virtual Phone.

The basic structure is:

[1] Message Identifier

State=0 Represents the state of the message in Virtual Phone and should not be modified.

0 = Received unread message (i.e. new message)

1 = Received and read message

2 = Stored unsent message (only applicable to SMS)

3 = Stored sent message (only applicable to SMS)

4 = All messages (only applicable to +CMGL command)

5 = All messages (only applicable to +CMGL command)

Do not change a Received message to a Sent message or visa versa. Never use states 4 and 5.

DataSize=8 The length of the Message Text

Data=656461717364617A4D

The Message Text, in hexadecimal followed by a check sum.

DCS=5 Data Coding Scheme. Values are:

8 Bits Encoding = 0

Default GSM Encoding = 5

PCount=0 Multi Part Options: Count

PCurr=0 Multi Part Options: Current

PId=0 Multi Part Options: Part Id

DtTimAbs=1

If DtTimAbs = 1 (absolute time) the date and time are absolute. If DtTimAbs = 0 the date and time are relative.

DtTim=3063866010 The date and time are in palm format

Add=+33658214566 The address of the SMS message

ProtocolId=0 Protocol ID. Values are:

Default Protocol = 0

Fax Protocol = 1

X400 Protocol = 2

Paging Protocol = 3

Email Protocol = 4

Ermes Protocol = 5

Voice Protocol = 6

ReplyPath=0 Reply Path. Values are: 1 = true or 0= false

SCeneter=+33668547854

Service Center number

SmsStore.db File

The following description is valid for the `SmsStore.db` file and are specific to SMS Delivery.

MsgIdentifier=1 Delivery Message Identifier

OthToRcv=0 Other To Receive: values1 = true or 0= false

RepDelivInd=0 Report Delivery Indicator: Currently not supported

SmsStoreSend.db File

The following description is valid for the `SmsStoreSend.db` file and are specific to SMS Submit.

SubId: Submit message identifier

DlvReq: Network Delivery Request

DupReq: Reject Duplicate Request

Log File

The log file, `VPAppATLog.log`, is generated by Virtual Phone. It contains all the exchanged AT commands and responses between Virtual Phone and Palm OS Emulator.

The following is an example of what the log may look like.

VPAppATLog.log

```
AT
OK
AT+CPMS=?
+CPMS: ( "SM" )
OK
AT+CPMS="SM"
+CPMS: 1,100
OK
AT+CPMS?
+CPMS: "SM",1,100,"SM",1,100,"SM",1,100
```


Index

A

Area Code 25
AT commands 3, 13
Available Networks 26
AvailableNwk.db 3, 5, 22, 61, 65

B

Battery Status 20
books
 see related information viii
Brand 19
Busy 54

C

Cell Id 25
COM1 9
COM2 9
Communication 3
Configuration 3
Connect 54

D

Date 51
documentation viii

E

European Telecommunication Standards (ETS) 2
European Telecommunication Standards Institute (ETSI) 2

G

Global System for Mobile Communications 2
GSM 2

I

Incoming Calls 53
Information 3

K

knowledge base viii

L

Last Dialed Phone Book 65
Location 25
Log File 69

M

manuals
 Palm OS Emulator viii
 Palm OS Programmer's API Reference viii
 Palm OS Programmer's Companion viii
 Telephony Manager viii
 Telephony Manager APIs viii

N

Network 3, 21

O

Outgoing call 54

P

Palm OS 3
Palm OS Emulator 3, 7
Palm web site
 documentation viii
 knowledge base viii
 training viii
Personal Identification Number 30
Personal Identification Number (PIN) 30
Personal Universal Key (PUK) 30
PhbFD.db 61
PhbLD.db 61
PhbME.db 61
PhbSM.db 61
Phone Book 3, 27, 28, 61, 65
Phone Model 19
Phone Number 19
Phone Revision 19
PIN 30
PIN1 31
PIN2 32
Properties dialog 8
PUK 30
PUK1 31

PUK2 32

R

Reg State 23

Registration Roaming 24

related information viii

 Palm OS Emulator viii

 Telephony Manager viii

Release 54

S

Search Mode 24

Security 3, 29

Serial Port 9

serial port 9, 52

Short Message Services (SMS) 3

SIM 31, 32

SMS 33, 56

SMS (Short Message Services) 66

SMS Files 66

SMS message 1

SmsSentStore.db 4

SmsStore.db 4, 56, 61, 66

SmsStoreSend.db 33, 66

SmsStoreSent.db 61

Speech Call 3

State 23

T

TCP 9, 10

telephony drivers 1

Telephony Manager 3, 13

telephony manager

 definition 3

training viii

V

Virtual Phone 1

VPAppATLog.log 4, 61, 69

VPAppCfg.db 3, 19, 61, 62

W

web site viii

 documentation viii

 knowledge base viii

 training viii
